




Installing WELTRAUM Software into windows PC.




Right Click on Setup File and click on Run As Administrator




Click Next




Select Folder to be installed (default folder is C:\WELTRAUM) Click Next to Proceed.



Click Yes




Click on Start Button.




Click Yes

WELTRAUM




Wait for Completion, at end of this process You will See screen as Bellow.




Here Select the Application to be Installed (in Case of Server , Database installation starts at End of the Process, If Client installation, Follow the Click Installation Process.)

Click Next to Proceed.




Along with Application Installation, SQL Server installation also starts. Wait to Complete all installations.


Once completed SQL Server installation show u screen as bellow



Click Close Button.




Click on Install PMS and POS Database Button




Finally you get Message as Process Completed.

Click ok to Close all Installer Screen.


Sharing the Installed Folder (for Client PC accessing)





Right Click on WELTRAUM folder-> Click on Properties.




Click on Sharing Tab




Click on Advanced Sharing





Check Mark on Share this folder, and then Click on Permissions.




Click on everyone (if not in the list click add button and select Everyone from list), Click on Full Control Check mark as above.


Click Apply->Ok , and close all Screens

Installing SQL Server management Studio.

In C:\WELTRAUM\SQLSERVER folder



Right Click on SQLManagementStudio_x86_ENU.exe




Run as Click on Administrator


Click Next to Proceed Installation. Install with default options.

Setting up IP for SQL Server


Windows start and Search for SQL Server Configuration manager




Run as Administrator




Click on Protocol for WELSQL2008R2 under SQL Server network Configuration (32 bit)




Click on TCP/IP if Disabled right click and Enable it



And Right click on TCP/IP and click on Properties




Click on IP Addresses Tab. Click on TCP Port and type 1433




Under SQL native Client Configuration (32 bit).

Click on Client Protocols; Enable all protocols by right click on Protocol name and Enable.




Server	Protocol
DESKTOP-P1INTAP	np
WELTRAUM-4\SQL...	tcp
WELTRAUM-4\SQL...	tcp
WELTRAUM-1\SQL...	tcp
192.168.1.10	tcp
WELTRAUM-2\MSS...	tcp
WELTRAUM-2\WEL...	tcp
WELTRAUM-1	np

Click on Aliases




At Right side pane , Right click and Click on New Alias.




**In Alias name type IP of Server pc.
 Port Number 1433
 Protocol TCP/IP
 Server is Your Computer name/ WELSQL2008R2
 Once done Click apply.**

Adding SQL Server port into Firewall Exception.


Open Control panel



Click on Windows defender Firewall




Click on Advanced settings




Click on Inbound Rules and Click on New Rule.


Click on Port then Click Next




Click on TCP , then click Specific local ports type 1433 , then Click Next




Click on Allow the Connection, Then Click Next



Check mark on All options.




Then Click Next




Type SQL as name and Click on Finish


Creating outbound Rules




Click on Outbound rules and Click New Rules




Click on Port and Click Next




Click on TCP and type port number and Click Next.



Click on Allow connection




Click on next



Type a name and Click Finish.

Installation into Client PC




Right Click on Setup File and click on Run As Administrator

WELTRAUM




Click Next

WELTRAUM




Select Folder to be installed (default folder is C:\WELTRAUM) Click Next to Proceed.




Click Yes

WELTRAUM




Click on Start Button.



Click Yes


WELTRAUM







Click on Client Installation, then Click Next

Type the SQL Server name (or IP of the Server PC) then Click PC





Click on Create Data Connection button



After successful installation below message shows.

